Urinary Catheter Insertion using Surgical ANTT





A red number denotes where Key-sites need protecting



Disinfect hands with alcohol hand rub or soap & water



Disinfect trolley using a disinfectant wipe§ creating a General **Aseptic Field**



Gather equipment and place on bottom shelf of trolley



Ask patient or a colleague to lift gown pre step 9

Request patient performs general perineal hygiene (if appropriate)



Disinfect hands with alcohol hand rub or soap & water*



Open catheter pack creating a Critical Aseptic Field (sterile drape) & position waste



Open equipment onto the Critical Aseptic Field using non-touch technique (NTT)



Pour 0.9% sodium chloride

into the sterile gallipot, protecting Key-Parts using a NTT



Disinfect hands with alcohol hand rub or soap & water§ (after donning disposable apron if required)





Don sterile gloves Apply fenestrated drape

(Critical Aseptic Field) over genitals and sterile receiver between legs to catch urine.



Clean urethral orifice

with 0.9% sodium chloride and sterile gauze



Insert sterile lubricating gel suspending penis with sterile gauze (if

applicable)



Remove and dispose of gloves, & immediately disinfect hands



Don a new pair of sterile gloves



Insert catheter using NTT by touching only plastic wrapping



Inflate balloon

with sterile water using a NTT. Withdraw the catheter slightly so as the balloon is sitting at the bladder neck.



Attach collection bag

using a NTT. Use a securement device to prevent urethral trauma.



Dispose of waste, Including apron & gloves, then immediately ...



Disinfect hands with alcohol hand rub or soap & water



Disinfect trolley using a disinfectant wipe§



Disinfect hands with alcohol hand rub or soap & water*